

Raspberry Wheat Ale

1. Fill your pot with 2 - 3 gallons of cool water (as much as your pot will comfortably hold at a full boil). Turn the heat on and bring the water to 160 degrees. Once the water has reached 160, put your crushed grains into the grain bag, pull the drawstring tight and put the grain bag into the pot of water. Dip the bag a few times to ensure that all the grains get wet. Turn off the burner or remove the pot from the heat source and steep the grains for 30 minutes. **Do not BOIL THE GRAINS.**

GRAINS USED: **1 lb. Light Crystal Malt (10°L)**

EXTRACTS USED: **7 pounds of Wheat malt extract**

2. When the 30 minutes are up, remove the grains from the water, drain, **without squeezing**, the grain bag. Remove the outer bag from the malt extract. Cut off some of the excess top of the bag holding the extract and carefully pour the extract into the pot. Stir the extract until it dissolves. **To avoid scorching the extract:** Do not return the pot to heat until all the malt extract syrup has been added and dissolved. Once the extract is thoroughly dissolved, turn the heat back on and bring the mixture ("wort") to a boil. **WATCH FOR BOIL OVERS WHEN ADDING HOPS**
3. Add hops according to the schedule below:
 - **1.25 oz Hallertauer Hops at 60 minutes (beginning of boil).**
 - **1/2 oz. of Saaz Hops at 20 minutes (end of boil).**
 - **1 tsp of Irish Moss at 20 minutes (end of boil).**
 - **1 can Oregon Fruit Raspberry Puree Add to secondary fermenter**
4. **Turn off heat and cool the wort. It is critical that you maintain sanitization as the wort cools.** When wort is at or below 80 degrees, carefully pour wort into a sanitized fermenter and top off with cool water to bring total volume to 5 gallons. Aerate wort well before pitching.

Use the following yeast options:

LIQUID YEAST: **WHITE LABS 320**

Follow the directions printed on the plastic vial. Sterilize the outside of the package before opening. Ferment between 65-75°F.

5. Attach your airlock and fill the airlock halfway with cooled boiled water. Put fermenter in a cool, dark place to begin fermenting. NOTE: A water bath may be used ensure the fermentation temperature stays in the 70-75 degree range. Use 2 or 3 16oz frozen water bottles, changing them out approximately every 8 hours as necessary. **Fermentation will be complete in 10-14 days.**
6. Bring two cups of water and 3/4 cup Corn Sugar to a boil and simmer for 10 minutes or microwave for 2 minutes. Add the sugar solution to your sanitized bottling bucket and rack (siphon) the beer onto the sugar solution. You are ready to bottle!

CAUTION: If finished volume is less than 5 gal, use 1 TBS less corn sugar per half gal

CHECKLIST:

YEAST AT ROOM TEMPERATURE

CLEAN EQUIPMENT

ICE

SANITIZE

DATE/TIME START: _____ DATE TO 2ND _____ BOTTLE/KEG _____

Original Gravity _____ Specific Gravity _____ Final Gravity _____

Wort Temperature at Pitch: _____

Fermentation Area Temperature: _____

NOTES:

DATE SERVED/COMMENTS: